


# SOME GUIDELINES FOR COLLECTING DATA WITH WIRELESS INSITE

Duc-Tuyen Ta

( [tuyentd86@gmail.com](mailto:tuyentd86@gmail.com) )

## A. RECEIVER

There are many way to set up **Receiver Set**:





Moving point, Route, and Trajectory require left-click for inputting segments and right-click for ending. But

- **Moving point:** allow us to select time spacing between adjacent position and total simulation time. The number of positions of receiver is automatically generated (evenly for each segment but not for all segments) and can be compute by total simulation time/time spacing.
- **Route:** enables us to select spacing sample in metter and the moving velocity.
- **Trajectory** is similar to Route except that A spline is fit to the control points and then individual transmitter or receiver points are located along the spline according to the spacing provided by the user in the set's property window.



In summary, we choice “Route” mode because it is easy for us to control.

- **Step A.1:** select segments by left-clicking. Note that:
  - The total length of the route should be **larger than 1024\*wavelength** so that we can have more than 2048 samples.
  - The segment should **not cross** the building. If not, the received powers at the hidden point would be very bad and this makes difficulties for training our future CNNs.
  - The minimum distance to transmitter should be larger than 15m so that the effect of fading is clear
- **Step A.2:** Go to Tx/Rx LAYOUT PROPERTIES



Select:

1	Spacing	$\text{WaveLength}/2 = 300/f_c/2$	Ex: 0.15 (m)
2	Velocity	1.4 (m/s) [walking speed: 5km/h]	Ex: 1.4
3	Height	1.5 to 2 m	Go to [Edit control points] and set up Z value


- **Step A.3:** Go to Receiver PROPERTIES and configure



## C. STUDY AREA

Should not be too large but it should cover all the Rx Route

## D. OUTPUT AND SAVING RESULT



- Please sure that you have at least checked “**Propagation paths**” and “**Received Power**” for Output Requests before running.
- After finishing the calculation, please go to the working directory of the project (saving place). You will see a folder with the name of the Study Area that you have defined.
- Please save at least two files: “**\*power\*.p2m**” and “**\*paths\*.p2m**”

In case that you have available hard drive, additionally saving “**\*.sqlite**” file will be a very good option for future use.

Name	Type	Size	Name	Type	Size
Downtown	File folder		errorlog	Text Document	0 KB
mapSF.city	CITY File	6,450 KB	SF3.Downtown.sqlite	SQLITE File	27,966 KB
mapSF.city	KMZ	1,616 KB	SF3.inputpower.t01.p2m	P2M File	1 KB
SF3.Downtown	DIAG File	8 KB	SF3.paths.t001_01.r002.p2m	P2M File	1,090 KB
SF3.Downtown	XML Document	55 KB	SF3.pg.t001_01.r002.p2m	P2M File	9 KB
SF3	SETUP File	6 KB	SF3.plt001_01.r002.p2m	P2M File	9 KB
SF3.bnx	TXRX File	3 KB	SF3.power.t001_01.r002.p2m	P2M File	11 KB
SF3.vw	VW File	1 KB	SF3.tloss.t001_01.r002.p2m	P2M File	9 KB